# **License Borrowing Guide**

(CLM version 2.13.0, 05.31.2023)

# **Borrowing a License from a License Server**

This Quick Guide will cover borrowing a license from the License Server for use off the company network.

The borrowing steps include:

- 1. Opening the CLM License Manager
- 2. Borrowing a License
- 3. Confirmation of successful license checkout in the Software
- 4. Return borrowed license

#### **1.** Opening the CLM License Manager



- Select your Windows Start Menu
- Scroll down to the Leica Geosystems folder
- Select "CLM License Manager"

#### 2. Borrowing a License



Select "Borrow"



CLM				- 0 ×
Licenses	Settings He	elp About		
Licenses	Usage (	Borrow license	×	Borrow + Add
Licens	ie	A floating license can be borrowed f the borrowing, the license will be tra used without a connection to the lice	rom a floating license server for maximum 90 days. During nsferred to this system as a node locked license and can be ense server.	
		Server YourServersName		
		Tourserversivanie	✓ <u>≺</u>	
		Show only borrowable licen:	ses (not already borrowed or in use)	
		License	Days	
		× Cancel	✓ Borrow	
	_			

he borrowing, the license sed without a connection	will be transferred to this sy to the license server.	stem as a node locked license	ays. During and can be
Server			
to all to all	<ul> <li>a</li> </ul>	L.	
Show only borrow	able licenses (not already b	orrowed or in use)	
License		Days	
> 0010	100 MOT 11 MA	5	
		2	
× Cancel			V Borrow

Loomer Q Roma poduct future, status, sport	censes Settings Help About				
Looma Dates Type > 0010 Bottowed Floating	Licenses Usage Q license, product, feature, status, type		(-	Borrow	+ Add
> 0010 Borrowed Floating	License	Status	Type		
	> 0010	Borrowed	Floating		e

- Type in your License Server's name
- You can turn on "Show only borrowed licenses"
- Select the red check mark

- Select the Entitlement you would like to borrow\*\*
- Type in the number of days you would like to borrow the license
- Then select "Borrow"

 The Entitlement ID is now listed in the CLM and the status has changed to "Borrowed"

**\*\*Note**: If you are not sure which Entitlement ID is the license you would like to borrow select the drop-down arrow next to it to see the product details.



## **3.** Confirmation of successful license checkout in the Software

Disconnect from the network and launch the Software. Change the License Server name from the License Server to "@localhost". Please see examples below:

In Register 360 PLUS change	the License Server to "localhost" under the License Tab	In Cyclone CORE change the License Server to "localhost" under
Cystere KLOSSTER IND PLUS	- 0 ×	Help/Set Switch License Server:
	Cened Lake Looke CoultsCloud Haining Reading Equal Speakers	💽 Cyclone - Navigator.Hexagon Compan — 🗆 🗙
Collapse Bundle Collap	Loonse Server, Teacher is under and a looner has been obtained. Status Looner is under and a looner has been obtained. Felgely	File Edit View Configure Create Tools User Apps Help
		📗 co 😪 🖻 📾 🛪 📲 🖆 🖉 🚅 💒 🛃 🛃
		📔 Set License Server Host 🛛 🗙
		Current: @localhost
		New: @localhost
	(b) moot	Enter your license server's host computer name, then press "Apply" to validate & save.
		Apply Close
In CloudWorx for AutoC "localhost":	AD type " <u>cwlicserver</u> " in the command line and change t	the License Server to
		Show License Information at start up
dify Analyze View Manage	Output Survey Rail Transparent InfraWorks Collaborate Help	Add-ins Express Tools Fe
Floor Plan Save UCS +Wall View P Align View Orientation	ord Clipping Hide Limit X Manager Outside Box Axis A Clipping - Hide Limit X Manager Outside Box Axis A Clipping - Regenerate Color Dens Points Mapping Off	ity Modeler S 1 Piero
[-][Top][2D Wireframe]	C License Server ×	
0	Input the CLM license server name or empty for local	
> <		
Prosp	localhost OK Cancel	
sbu		
Setti		

Note: If the License Server does not change you can change the name to @localhost under Start Menu/Leica Geosystems/Set License Server.



- when it has to be **right** 

ML			
censes Settings Help About			
Licenses Usage Q license, product, feature, status, type		(+	Borrow + Add
License	Status	Туре	
> 0010	Borrowed	Floating	5



CLM	Settings	About	- 0
Licenses	Usage	Q	+ Borrow + Add
Lic	ense	Status	Туре
		New licenses can be added via Add or	r Borrow

### 4. Return borrowed license

- Open the CLM License Manager from the Start menu
- Select the Return icon



- CLM will ask if you would like to return the license back to the License Server
- Select "Return"

• The license has now been returned to the License Server



- when it has to be **right**